# **IMS300 SURVEILLANCE SYSTEM**

# **USER MANUAL**

# Introduction

### 1. Summary:

«IMS300 Surveillance System User Manual» introduces the software features and configuration operation of IMS300. Please go through this user manual before operating.

### 2. Symbol agreement:

The meaning of symbols hereinafter is as following:

Symbols	Statement		
[ ]	"[]" refers interface, menu and data sheet, e.g. "[Add User] interface"		
[ ]	"[] "refers button, e.g. "click [OK]"		
	Introduction: make some complement explanation to the contents.		
A	Warning:prompt the warning in order to avoid damage caused by improper operation.		
Δ	Note: prompt operation notes in order to avoid data loss and device damage caused by improper operation.		

# TABLE OF CONTENTS

1 Introduction	3
1.1 System Introduction	3
1.2 Configuration requirement	3
2 Progarm Install	4
3 Quick Guide	8
3.1 The client login	8
3.2 Home Page Introduction	8
3.3 Device Management	9
3.3.1 Add Device	9
3.3.2 Delect and Modify Device	12
4 Video Surveillance	14
4.1 Real-time Video	14
4.1.1 Real-time preview	14
4.1.2 Local Video	15
4.1.3 PTZ Setting	16
5 Video Playback	19
5.1 Video Playback	19
5.2 Video cut and download	21
6 EMap	24
6.2 Edit Map	25
6.3 Add HotSpots	27
6.4 Edit HotSpots	28
7 Alarm Event	29
7.1 Event Center	30
7.2 Event Handling	30
8 Configuration Management	32
8.1 Basic Settings	32
8.2 File Settings	33
8.3 Plan Configuration	34
8.3.1 View Plan	34
9 User Management	34

# 1 Introduction

#### 1. 1 System Introduction

IMS300 is a professional surveillance system software which support muti-user, multi-window and multi-language, voice talk, EMap, alarm and etc. IM300 is compatible with various access devices. This is a stable, reliable and easy operation system.

IMS300 is software applications for embedded network CCTV monitoring equipment including NVR,IP Camera, IP Dome, PCNVR, decoding device and AV decoding card, it can support real-time preview, remote configuration, recording, playback, alarm, electric map and etc..

- > Simple Component Design: Multiple components can be installed in one PC For a highly integrated.
- > 550 end users System: Add as much as 50 end users, fully meet the various system permissions management solution.
- Find back the password with the super user permissions batch function.
- ➤ Interface container processing mode: Elaborate method of container handling, simplifies the screen and single switch, significantly improved screen operation experience.
- Channel management mode: Add the channel management mode, adapt the IP monitoring more.
- ➤ Compatible with custom tools to generate configuration files.
- Consider more for UE: Provide visual image type control panel based on the UE, reverse the USES the required type.

Need only visible display mode:on client component interface elements, joined the need only visible display mode, the calendar, time, the toolbar, the system info, etc., to join the design pattern.

### 1.2 Configuration requirement

Lowest requirement of client to run IMS300 see below table 1-1:

Table 1-1 lowest configuration

Parameter	Introduction	
CPU	Intel Pentium IV 3.0 GHzor more	
RAM	DDR3 1GB	
HDD	Available space is more than 10 GB	
Operation	Microsoft Windows 7, Microsoft Windows 8.1, Microsoft Windows	
System	10	
Display	Resolution above 1024×768, suggest to use resolution of 1280×1024	
Resolution	Hardware support version above DirectX9.0c	

# 2 Progarm Install

#### Below shows detailed installation procedure of IMS300:

Step one: Double click IMS\_300\_V1.1.2 Trial.exe to install this program;

Step two: Complete the installation following the guide, click [Next], see "Figure 2-1":




Figure 2-1

Step Three: Change [Name] and [Company], click [Next], see Figure 2-2:




Figure 2-2

Step Four: Select installation path, the default path is: C:\Program Files (x86)\IMS300), then click  $\llbracket$  Next  $\rrbracket$ , see Figure 2-3:




Figure 2-3

Step Five: Click [Next], see Figure 2-4:



Figure 2-4

Step Six: Click [Next], see Figure 2-5:




Figure 2-5

Step 7: Being installed files, please wait. see figure 2-6:




Figure 2-6

Step 8: Click [Finish], the installation is complete. As shown in figure 2-7:




Figure 2-7

# 3 Quick Guide

### 3. 1 The Client Login

Double-click to run it, open login page, as shown in figure 3-1. Input Username and password, Click [Login] to log into the client.




Figure 3-1 The client login

Check [Save password] and [Auto login], it will log in current user next time by default.

### 3. 2 Home Page Introduction

Clients homepage as shown in figure 2-6, it can be divided into sub-window area, business logic, alarm statistics, tool sets, alarm event.




Figure 3-2 Clients homepage

- Click in right corner interface, switch to another user logged on to the client;
- Click in right corner interface, lock the screen. After locking the screen, not able to operate the client. To unlock, need to be in [the screen is locked, enter the current user name and password to unlock] enter the current username and password in the prompt box to unlock;
- Click in right corner interface, client interface can be minimized interface display;
- Click in right corner interface, client interface can be displayed in full screen;
- Click in right corner interface, be able to exit the client.

#### 3. 3 Device Management

#### 3.3.1 Add Device

For the first time using the software, it is needed to add a device. Device online column shows all online device of current LAN.

Method 1: (1) Click 【Resource Management】 → 【Add Device】, As shown in figure 3-3:




Figure 3-3 Resource Management

(2) Complete device information, then click  $\$  Save and Continue  $\$  or  $\$  Save  $\$ , then can see the device in the Managed Devices column. see "Figure 3-4":




Figure 3-4 Decive Information

Method two: (1) Click [Resource]  $\rightarrow$  [Refresh], see "Figure 3-5":




Figure 3-5 Managed Devices

(2) Complete the previous operation, the online device will show in the Device Online, select device you wanna to add, then click  $\ Add \$ , you will see added device in the Managed Devices, see "Figure 3-6":





Figure 3-6 Managed Devices

#### 3.3.2 Delect and Modify Device

In[Managed Devices]choose the added device, then click , can delect the device.
In[Managed Devices]choose the added device, then click, can modify the device. see figure 3-7:



#### **IMS300 Client User Manual**

Figure 3-7 Add the device's network parameter

On this interface, user can change the device's parameter, like device's name, login type, device IP, device port, username, password and manufacturer etc. Then input administrator's password, and click Save to finish the parameter adding.

## 4 Video Surveillance

#### 4. 1 Real-time Video

IMS300 support realtime preview, local recording, snapshot, PTZ control etc.

#### 4.1.1 Real-time preview

Steps show as below:

Step 1: click [Realtime Monitor] in business logic area, the system will show the realtime monitor interface;

Step 2: In the device list at the right side of interface, choose the channel and drag to video window; It will show the realtime monitor interface in video window. See below figure 4-1.




Figure 4-1 Real-time Video

No.	Item	Description		
1	Stream Info	Show the channel stream information		
		PTZ: control operations direction up, down, left, right, upper left, upper right, left blew, right blew;		
		<ul> <li>Recording: turn on or turn off (Recording document was default save under default software local recording path);</li> </ul>		
		• Capture: capture current channel image (capture file was default save under default software local capture file path);		
2	Shortcut	Recording playback: used for current channel video;		
	Operations	Region image: turn on or turn off electric enlargement;		
		Talkback: turn on or turn off pronunciation talkback;		
		Voice: turn on or turn off audio.		
3	Local	Used for switch local and video wall.		
4	Picture segmentation mode	Used for set screen segmentation mode.		
5	Aspect Ratio	Choose video aspect ratio, which used to adjust picture size to original ratio or fit window		
6	Save View	Saving current window layout and opened video source as the same image plan.		
	W. 1.G. 1	After saving image plan, it can be performed at view plan of [Plan Configuration]		
7	Wheel Guard	Turn on or turn off current channel wheel guard		
8	Full Screen	Switch Video Window to full screen, double-click video window or press Esc or click right click to choose "exit full screen".		
9	Device	Display equipment and channel.		
10	PTZ	Setting up PTZ preset point, point to point wheel guard and auxiliary function .		

#### 4.1.2 Local Video

Recording operation step:

Step 1:Click video window at bottom right of real-time preview or right click to choose [open recording ].




Figure 4-2 Local video

Step 2: Once recording finished, click or right click [closed recording].

#### 4.1.3 PTZ Setting

Achieving speed dome camera full range monitoring by setting PTZ direction, preset point and point to point wheel guard.

Previewing speed dome camera monitoring image, click speed dome camera preview interface and the PTZ tabs at right side of the interface, the system display PTZ interface ,see figure 4-3.




Figure 4-3 PTZ control

Parameters	Description	
3D Positioning	Opened 【3D Positioning】, controlling PTZ by mouse relative position in preset window.	
Mouse Simulating	Using mouse to control eyeball camera.( the effect is same as 【Open PTZ】)	
Direction leav	Achieved 8 directions PTZ operation, up down left right upper left upper right, bottom	
Direction key	left, bottom right.	
	Clicking one point at video monitor interface, PTZ will turn to the point, and the point	
	will move to middle point of screen, support zoom function, using mouse to drag in the	
SIT	monitor screen interface, drag frame support 1-36anamorphosis,pressing on mouse from	
	upper left to bottom right, that will be larger, Pressing on mouse to drag, which from	
three-dimensional positioning	bottom right to upper left, that will be small . the frame size will be smaller,the multiple	
	will larger, otherwise will be smaller. (the function just only use mouse to control.)	
Step length	Used for PTZ turning speed, achieve 1-8 different turning step length setting.	
Zoom	Control speed dome camera and do zoom operation.	
Focusing aperture	For focus control, adjust the clarity. Adjust speed dome camera aperture, adjust brightness	
	Using direction button to turn PTZ to needing position, entering preset result in preset	
Preset	frame, put the button to save.	
Point to point wheel guard	Achieve different wheel guard auto carry out.	
Aux Function	Light on/off, Aux1 on/off, Aux2 on/off.	

#### Preset Setting:

Step 1: Moving camera to target position by clicking Direction Key

Step 2: Click preset point tabs:

Step 3: Input preset point name.;

Step 4: Click Setting, current monitoring area of the camera will be one preset point

Set other preset at drop-down menu by clicking [Position]

#### Cruise Setting:

Step 1: Click [Cruise];

Step 2: Click+, [New Cruise] pop up;

Step 3: After parameter setting, click [Save], See figure 4-4:



Figure 4-4 New Cruise

Select cruise at Cruise between points tab, Click ▶, Cruise start; Click, Modify setting cruise line.

# 5 Video Playback

Recording could be checking by channel, time and different type and replay/edit.

### 5. 1 Video Playback

Detailed playback operation steps:

Step 1: Click [Playback] (see Figure 3-2, section 2), it will show [Playback] interface, see figure 5-1:




Figure 5-1 Video playback

No	Item	Description
		Screenshot: Screenshot on current recording;
1	Shortcut Key	• Area Image: Elec-amplify on/off;
		Voice: Adjust voice of current recording.
		• Stop: Stop playback on current channel;
		Pause: Pause/play on current channel;
2	Play Toolbar	• FF: Fast forward on current channel;
		• Synchronization: Multi-channel replay Synchronization;
		• Slow down: Slow down replay on current channel;
		• Speed up: Speed up replay on current channel.
		Stop all: Stop all replay;

3	Window Shortcut	Division: Division current replay user-defined	
		• Full Screen: Switch to Full Screen.	
		• Left: Time schedule move left;	
		Right: Time schedule move right;	
4	Time Schedule Control	● Zoom in: Time schedule unit amplification;	
		Zoom out: Time schedule unit reduced;	
		Watermark: Watermark for current recording.	
5	Time Schedule Bar	Choose replay position on current channel.	
6	Point Tree	Device/channel display.	
7	View Tree	Date of recording	
8	Advanced Search	Recording searching.	
9	Video Cut/Download	Cut/Download Video.	

Step 2: Choosing device channel at upper right side.

Step 3: Choosing starting/ending time, click [search]

Available recording will be shown at time schedule bar when searching finished, Figure 5-2:




Figure 5-2 Recording search

Step 4: Choosing target channel, click , recording replay, see figure 5-3




Figure 5-3 Playback

#### 5. 2 Video cut and download

Step1: Click from the clip download area(No.9 area of Diagram5-1) of Playback interface. Then mouse will show as in time bar.

Step2: Left click to select start point at the channel time bar which want to clip, Then left Click again at another position to select the end point. See figure 5-4:




Figure 5-4 Video cut and download

Step3: Right click at the time bar to select 【Plan Add】 after you select the starting point and end point; Step4: Continue click at the video clip area (No.9 area of figure 5-1)), see figure 5-5;




Figure 4-5 Video download

Item	Name	Description
Downloading	Downloading	Display the current progress of the download tasks
Downloaded	Finish	Display download task has been completed
All Start	Start	Start all download tasks in list
<b>•</b>	Start/ Suspend	Start to download current task
×	Cancel	Cancel download current task

#### **IMS300 Client User Manual**

	0	Oman the folder vyhich vides devymled
	Onen	Open the folder which video download
_	open.	open me roteer which views do which

Step5: click or To download of editing video

Step6: click Downloaded to check the video clip after downloaded, see figure 5-6:




Figure 4-6 Finished list

Item	Name	Instruction
All Delete	Delete all	Remove all finished download in list
<b>•</b>	Play	Play currently finished download
	Open	Open the folder where video download
<b>⋖</b>	Cancel	Remove currently finished download

# 6 EMap

EMap can quickly learn the location of the camera, and alarm host deployed, it is closely related to alarm function, when alarm occurs on the map, there is alarm hint, and according to this, we can take immediate protect action.

#### 6.1 Map add

EMap associated with groud, a groud can add one EMap.

The specific steps of the add EMap as below:

Steps 1: Click **[EMap]** at window area(see figure 3-2 picturre 1).

System display **[EMap]** interface, see figure 6-1:




Figure 6-1 EMap

Step 2: After add EMap name, click[Preview] to find pic file in PC, click [OK] to complete add ing EMap. See figure 6-2:




Figure 6-2 Map Add

Step 3:After success to add EMap,it will turn to defulted [Preview Model]. After add EMap,see figure 6-3:




Figure 6-3 EMap Adding Complete Interface

 $\wedge$ 

: The map pic format should be png,jpg,or bmp.

### 6.2 Edit Map

The spcific steps of editing map as below:






Figure 6-4 Edit Model

Step 2:Click [Edit Map], see figure 6-5:




Figure 6-5

Step 3: Choose map, modify the name and click 【Save】 to finish the map modification. Delete the current map operation:

Click  $[Edit Mode] \rightarrow [Delete Map]$  to delete the current map in the menu.

### **6.3 Add HotSpots**

Set submap of related map by hotspts configuration under editor state of the map.

Adding hotspots steps:

Step 1: Click 【Add Hotspots 】 under editor mode of the map ,see figure 6-6.




Figure 6-6 Add HotSpots

Step 2: Fill in the map name, click 【Browser】 to find the photos in the local PC, choose one photo and click 【OK】 to add this map ,see figure 6-7




Figure 6-7 HotSpots Adding Complete Interface

When you finish all the above steps, you can click the hotspots icons to go into the submap.

## **6.4 Edit HotSpots**

You can edit the hotspots when it is necessary:

Step 1: Choose the hotspot you want to edit and click 【Edit Hotspot】, see figure 6-8




Figure 6-8 Edit HotSpots

Step 2: Modify the name and photo of hotspots map, click 【Save】 to finish the modification. Delete current hotspot map operation:

Click  $\[$  Edit Mode  $\]$   $\to$   $\[$  Delete Hotspot Map  $\]$  to delete the current map in the menu.

# 7 Alarm Event

There are two parts of alarm centre event, one is event center, another is event handling:

#### 7. 1 Event Center

IMS300 alarm center supports check and deal with all kinds alarm events.see figure 5-1:




Figure 7-1 Event Center

### 7.2 Event Handling

[Event Handling]Show event by channels




Figure 7-2 Event Handling

# **8 Configuration Management**

### 8. 1 Basic Settings

Configure the basic parameters of the client when users log in the IMS300 for the first time. Detailed process as described below:

Step 1: Click [Basic Configuration] of Tool in the home page of the client. (See area 4 of Figure 3-2) [Basic Configuration] see figure 8-1:




Figure 8-1 Basic Configurations

Item	Description		
Log save time	Set the save time of log, 7day, 15days, 30days, 60days and 90days optional.		
Display Ratio	Set the display ration of video. Full screen, original size, 16:9 and 4:3 optional.		
Play Performance	Set play performance of video play and video realtime preview. Quality priority		
	and fluent priority optional.		
Snapshot Format	Set the picture format for sharpshooting and saving. JPEG and BMP optional.		
Time Scale	Set time scale of client, 12-hour and 24-hour optional.		
Time Settings	Set client time, sync local time by clicking sync time.		
SystemLanguage	Set the language of client, Chinese and English optional.		

Step2: Click[save] after finish setting.



: Click [default] to reset local configuration

## 8. 2 File Settings

Detailed process as described below:

Step1: Click [Document Configuration] in the home page of the client(see figure 3-2 area 4).

【Basic Setting】 interface as figure 8-2:




Figure 8-2 File Setting

Name	Parameter	Description
	Video Shade	Set video shade alarm
	Motion Detection	Set motion detection alarm
	Video Lost	Set video lost alarm
Audio Alarm	Tripwire Intrusion	Set tripwire alarm
	Region Intrusion	Set Region intrusion alarm
	Face Detection	Set face detection Alarm
	Disk Error	Set disk error alarm
	External Alarms	Set external alarm
	Capture Path	Set save path of captured pictures
File Path	Recording Path	Set save path of recording videos
	Download Path	Set save path of download video

Configure Path Set save path of local configuration

Step2: Click [Save] after finishing the settings.



: Click 【Reset】 to restore all file configuration to default..

### 8. 3 Plan Configuration

#### 8.3.1 View Plan

Steps of plan configuration as following:

Step1: Click [View Plan] on home page(See Area 2 of Figure 3-2)

[Plan settings] interface as figure 8-3:




Figure 8-3 Plan settings

# 9 User Management

Detailed setting steps see below:

Click [E-map] on home page( Area 1 of Figure 3-2)

Step1:Click [User management] on the tool list of home page

【User Management】interface as figure 9-1:

#### **IMS300 Client User Manual**




Figure 9-1 User Management